



DOSPrint

Version 2003.03.03



Copyright © 2003

<http://www.andtechnologies.com>



A.N.D. Technologies, Inc.

4104 24th Street #627

San Francisco, CA 94114

USA

Conditions for using DOSPrint

- DOSPrint is free for general use without restriction.
- DOSPrint may not be resold.
- DOSPrint is provided as is, without any warranty or guarantee. A.N.D. Technologies, Inc. is not responsible for any data loss resulting from your use, non-use, or misuse of DOSPrint.
- Technical support is not available.

What is DOSPrint?

DOSPrint is software which captures LPT ports to any print queue.

(Requires Windows NT 4.0, 2000, or XP - Windows 9x is not supported)

- DOSPrint can capture LPT1-LPT9 to any local or network print queue.
- Local print queues do not need to be shared.
- Capture directly to NDPS printers without requiring a legacy NetWare print queue.
- Capture directly to local LPT, USB, or TCP/IP printers without requiring sharing.
- Runs in the system tray for easy access.

DOSPrint comes in 2 flavors.

DOSPrintUI.exe - A user-mode GUI which requires a local administrator logon or equivalent.

DOSPrint.exe - A combination service/GUI which allows capture port assignments via command-line or through the system tray applet, and works with all logged on users.

Using DOSPrintUI

Run DOSPrintUI.exe, either manually, or via startup shortcut, etc.



Double-click or right-click on the icon in the system tray for options. There is no need to use DOSPrintUI if the DOSPrint service is running.

Note: DOSPrintUI will not work for local non-administrators.

Installing the DOSPrint service

DOSPrint.exe is a service. Nothing will occur if DOSPrint is not installed and running as a service.

To install DOSPrint:

Copy DOSPrint.exe to the SYSTEM32 directory.

Type: dosprint install

Type: net start dosprint

Batch file example:

```
@echo off
```

```
copy d:\path\dosprint.exe %SystemRoot%\system32
```

```
dosprint install
```

```
net start dosprint
```

Removing the DOSPrint service

Type: dosprint remove

Type: del %SystemRoot%\system32\dosprint.exe

Using DOSPrint when the service is running



Double-click or right-click on the icon in the system tray for options.

Command line options:

DOSPrint lptX printerName Capture lptX to printerName

DOSPrint lptX /d Remove lptX capture

DOSPrint status Display capture status